TS1000 TS2000 TS2100

Robot Controller

INSTRUCTION MANUAL

TS1000/TS2000 ROBOT CONTROLLER COMMUNICATION MANUAL

Notice

- Make sure that this instruction manual is delivered to the final user of Toshiba Machine's industrial robot.
- Before operating the industrial robot, read through and completely understand this manual.
- After reading through this manual, keep it nearby for future reference.

TOSHIBA MACHINE CO., LTD.

TOKYO, JAPAN

Copyright 2002 by Toshiba Machine Co., Ltd. All rights reserved.

No part of this document may be reproduced in any form without obtaining prior written permission from Toshiba Machine Co., Ltd.

The information contained in this manual is subject to change without prior notice to effect improvements.

Preface

This manual describes serial communication between the robot controller and peripheral devices. It covers such subjects as connecting communication channels and setting communication modes. It also describes communication protocols, communication commands and data format, and presents information on how to operate the robot with data communication and how to handle communication dialogue with controller programs.

Before reading this manual, we ask that you first read and understand the contents of the following user manuals.

- Startup Manual
- Operator's Manual
- Robot Language Manual
- Interface Manual

This Manual is divided into five sections:

Section 1 Introduction

This section presents an introduction to the communication functions provided by the SR Series robot system.

Section 2 Communication Port Specifications

This section presents information on port configurations, hardware interfaces, communication modes, etc.

Section 3 Communication via COM port

This section discusses the protocol for communication between the external device and robot program.

Section 4 Communication via HOST port

This section describes the communication protocol, commands, and robot program files as related to communication with the host computer.

Section 5 Robot Operation Sequences

This section presents examples of how to use communication commands to control robot operation.

Table of Contents

			Page		
Section 1	Ins	truction	1-1		
Section 2	Co	mmunication Port Specification	2-1		
2.1	Port C	onfiguration	2-1		
2.2	Conne	ections	2-2		
2.3	Communication Specifications				
	2.3.1	COM Port	2-2		
	2.3.2	HOST Port	2-3		
2.4	Comm	unication Parameter	2-4		
Section 3	Co	mmunication Via COM Port	3-1		
3.1	Comm	unication with a Robot Language Program	3-1		
	3.1.1	PRINT Command	3-1		
	3.1.2	INPUT Command	3-4		
	3.1.3	Clearing Communication Buffer	3-6		
3.2	Progra	mming Examples for Communication			
	with a Robot Language Program				
	3.2.1	Program Branching	3-7		
	3.2.2	Correcting the Position of the Robot	3-11		
Section 4	Co	mmunication Via HOST Port	4-1		
4.1	Transr	mission Protocol	4-1		
4.2	Transmission Format				
	4.2.1	Text	4-2		
	4.2.2	Data Section Format	4-3		
4.3	Commands				
	4.3.1	List of Commands	4-4		
	4.3.2	Commands and Operation Modes	4-6		
	4.3.3	Details of Commands	4-8		
4.4	RAM Files				
	4.4.1	User Files (Work files)	4-63		

		Page
Section 5	Robot Operation Sequences	5-1
5.1	Basic Operation	5-1
5.2	Program Download	5-1
5.3	Reinitializing and Starting a Stopped Program	5-1
Section 6	Appendix	6-1
6.1	ASCII Code	6-1

Section 1

Introduction

This manual describes hardware and software related to serial interfaces between the controller and host computer. It is possible to perform the following with such serial communications:

- (1) Upload and download programs and positional data;
- (2) Erase programs and positional data;
- (3) Select programs;
- (4) Externally control the robot with the following signals:
 - a) Start, Stop
 - b) Program Reset, Step Reset, Cycle Reset and Output Signal Reset
 - c) Servo OFF;
- (5) Monitor the status of the robot;
- (6) Communicate and control in robot language including:
 - a) Inputting values from an external device into variables in a robot language program;
 - b) Outputting variables and messages from the robot language program.
- (7) Monitor for robot errors:

The basic arrangement of the communication interface is shown in Figure 1.1. In this Manual, we treat only the external device and host computer.

There are two types of communication protocols. One, simple protocol, is used for file transmission and robot operation. The other, non-protocol, is used for (and only for) exchanging simple messages back and forth between the robot program and the external device.

TS1000/2000 robot controller




Fig. 1.1 Communication interface configuration

Section 2

Communication Port Specifications


2.1 Port Configuration

The TS1000 controller has two (2) serial communication ports which are used for the external device and host computer. The TS2000 controller allows addition of one (1) optional serial port, in addition to the above communication port.

The COM1 and COM2 ports correspond to the external devices, and the HOST port to the host computer.

2.2 Connections

The port 1 and port 2 should be connected, using an RS232C cross cable (D-SUB; 9-pin). (For details, see the Interface Manual.)



2.3 Communication Specifications

2.3.1 COM Port

Table 2.1 COM1 port communication specifications

Item	Specification		
Interface	RS232C		
Synchronous system	Start-stop synchronization system		
Communication system	Full duplex system		
Communication rate	300, 600, 1200, 2400, 4800, 9600, 19200, 38400 bps		
Data format	ASCII code		
No. of bytes	Max. 256 bytes		
Data structure	Data length: 7 or 8 bits		
	Parity: None, odd, even		
	Stop bit: 1 or 2 bits		
Protocol	Non-protocol		
Timeout	No timeout		
Fault recovery	No special protocols are used.		

Note: The communication rate and data structure are specified in the user parameter file. (For details, see Para. 2.4.)

The COM2 port is an option of TS2000.

2.3.2 HOST Port

Table 2.2 HOST port communication specifications

Item	Specification		
Interface	RS232C		
Synchronous system	Start-stop synchronization system		
Communication system	Half-duplex system		
Communication rate	300, 600, 1200, 2400, 4800, 9600, 19200, 38400 bps		
Data format	ASCII code		
No. of bytes	Max. 255 bytes		
Data structure	Data length: 7 or 8 bits		
	Parity: None, odd, even		
	Stop bit: 1 or 2 bits		
Protocol	Without checksum, simple protocol		
Timeout	10 sec. (character receiving intervals)		
Fault recovery	Command is re-sent from the host computer. No special protocols are used.		

Note: The communication rate and data structure are specified in the user parameter file. (For details, see Para. 2.4.)

2.4 Communication Parameters

The communication rate and data structure of port 2 are defined in the user parameter file.

Communication is performed according to the contents defined under [U06] of the user parameter file (USER.PAR) in the RAM drive.

TS1000

```
[U06] Serial port setting
{Speed} (38400, 19200, 9600, 4800, 2400, 1200)
{Character} (7, 8)
{Parity} (0: Without, 1: Odd, 2: Even)
{Stop bit} (1, 2)
= 9600 8 0 1
= 38400 8 0 1
```

- = (Speed) (Character length) (Parity) (Stop bit length) ←
- ← COM1 port setting
- = (Speed) (Character length) (Parity) (Stop bit length)
- ← HOST port setting

TS2000

```
[U06] Serial port setting
{Speed }(38400, 19200, 9600, 4800, 2400, 1200)
{Character}(7, 8)
{Parity }(0:Without, 1:Odd, 2:Even)
{Stop bit }(1, 2)
{COM1}
= 9600 8 0 1
{HOST}
= 9600 8 0 1
{COM2}
= 9600 8 0 1
```

[COM1]

```
= (Speed) (Character length) (Parity) (Stop bit length) ← COM1 port setting

[HOST]

= (Speed) (Character length) (Parity) (Stop bit length) ← HOST port setting

[COM2]

= (Speed) (Character length) (Parity) (Stop bit length) ← COM2 port setting
```

(Speed) : Select the speed for data communication from the following six (6)

rates.

38400 : 38400 bps 19200 : 19200 bps 9600 : 9600 bps 4800 : 4800 bps 2400 : 2400 bps 1200 : 1200 bps

(Character length) : Specify the length of characters to be transferred.

8 : 8 bits 7 : 7 bits

(Parity) : Specify the parity of characters to be transferred.

0 : Without parity

1 : Odd-number parity2 : Even-number parity

(Stop bit length) : Specify the stop bit length of characters to be transferred.

Stop bit 1
 Stop bit 2

Example: TS1000

Set value = 9600 8 0 1 = 38400 8 1 1

"Speed 9,600 bps, character length 8 bits, without parity and stop bit 1" are specified for the COM1 port.

"Speed 38,400 bps, character length 8 bits, even-number parity and stop bit 1" are specified for the HOST port.

Section 3

Communication Via COM Port

Non-protocol communication is used for exchanging messages between the external device and a robot language program and for printing out files.

The SCOL robot language provides two (2) commands for data communication; PRINT and INPUT.

The functions as described in the simple protocol cannot be used for the non-protocol data communication. Also, response to data received by the controller and timeout check are not processed at all.

3.1 Communication with a Robot Language Program

Data communication with a SCOL robot language program can be performed using the PRINT and INPUT commands. For more information on the SCOL robot language, see "Robot Language Manual".

3.1.1 PRINT Command

The PRINT command allows you to send out a specified character string or the value of a variable from the controller. The format of the PRINT command is shown below:

PRINT_<channel>.]{<character string>|<expression>}[,{character string> <expression>}] ...[,CR]

<channel>:

Specifies the communication channel over which the data is to be transmitted. One of the following should be specified as the channel.

COM1 : COM1 port

COM2 : COM2 port (option of TS2000)
TP : Screen output to teach pendant

Unless <channel> is specified, data is transmitted to the teach pendant.

<character string>:

The character string to be transmitted is specified by enclosing that string in double quotation marks (").

<expression>:

Constants, variables, and expressions (made up of constants, variables, arithmetic operands and functions) may be specified.

CR:

CR is used when the record end code (0DH) is added to the last of sending data.

Ex.: PRINT COM1, "INPUT DATA = ", -1000.0/3, CR

Commas are used to separate any multiple character strings or expressions specified in the PRINT command. Character strings are enclosed inside double quotation marks, and everything inside of those double quotation marks is transmitted in ASCII code. Expressions are first solved, and the result is sent as a 12 character block of fixed length (with the result pushed over to the right of that block). Should the result of the expression be an integer, that result is sent as a Base 10 number having a maximum of ten places (digits).

Should the result of the expression be a real number, the result is sent as a number having an integral part with a maximum of four -digits and a decimal part with a maximum of three digits (for a maximum of eight places counting the decimal point). (For example, the number 2315.753 has a four digit integral part (2315) a three digit decimal part (753), and a decimal point for a total of eight places. One space is in front of the number is allocated for the sign (+ or -) of that number, although the sign is omitted if it is plus (+). The number is sent in a 12 character block, with the number pushed over to the right. The remaining spaces are filled with space codes (20H). The number itself is sent in ASCII code. The commas used to separate character strings or expressions in a PRINT command are themselves not transmitted. When multiple character strings and/or expressions are specified with the PRINT command, the controller will send out these character strings and/or expressions as a single text.

Ex.: When the above example program is executed, the following data are transmitted.

INPUT DATA = -333.333 (CR)

Note: CR signifies the record end code (0DH).

3.1.2 INPUT Command

As opposed to the PRINT command, which is used for transmitting data, the INPUT command is used for receiving data. The only data which may be received by the controller are integers and real numbers. Data received by the controller is put into a variable (in a robot language program) specified by the INPUT command. This data can be referred to later in the program to operate the robot.

The format of the INPUT command is shown below:

INPUT (<channel>,) <variable> (<variable>), (<variable>...

<channel>:

Specifies the communication channel over which the data is to be received. One of the following should be specified as the channel.

COM1: COM1 port

COM2: COM2 port (option of TS2000)
TP: Key input from teach pendant

Unless <channel> is specified, the controller receives data from the teach pendant.

<variable>:

Specifies the variable in the robot program into which the data is to be entered.

Ex.: INPUT COM1, N1, N2

Commas are used to separate two (2) or more variables specified in the INPUT command. The controller waits until data comes in over the communication channel specified by the INPUT command. Add a record end code (0DH) to the end of data which is sent to the controller. When multiple units of data are to be sent to the controller, the individual data units should be separated with commas before being transmitted.

When more units of data are received by the controller than was specified with the INPUT command, the surplus data are ignored and used for the next INPUT command. If less units of data are received by the controller than was specified with the INPUT command, the controller waits until the surplus data reach.

Note 1)

The controller starts reading any data sent to it only after an INPUT command is executed. Data are set in the ring buffer, and the input data are picked up according to the request of the INPUT statement.

Any data received before the INPUT command is executed may be ignored. Take careful precautions when determining the data transmission timing.

Note 2)

Should program execution be suspended while the controller is waiting for data to come in (as directed by an INPUT command), the execution of the INPUT command will be cancelled. Should the program be resumed, program execution will start from the step following the INPUT command. Any variables for which data was not yet received when the program was suspended will be treated as 0.

You should keep this in mind when writing your robot language program, i.e., you should arrange your program in such a way that it will still function properly even should the controller (mistakenly) treat input values as 0. One way to do this is to have the controller ask the host computer for confirmation (retransmission) whenever the controller receives a 0. Another way to do this is to add on check-sum data (to the data to be transmitted) and check the validity of the received data. (For programming examples, see Para. 3.2, "Programming examples for communication with a robot language program.")

Note 3)

In the step operation mode, which is one of the test operation modes, when the INPUT command is executed, the program enters the wait state until data are received. The same holds true when an INPUT command is executed directly.

Note 4)

When an INPUT command is to be used to receive multiple variables transmitted as one text from the host computer, individual numerals should be separated in the text with commas.

3.1.3 Clearing Communication Buffer

If the number of data the controller has received is larger than the number of data specified by the INPUT command, such data are stored in the communication buffer and used at request of the next INPUT command. If data is left in the communication buffer, unexpected data will reach by the INPUT command. To clear the data left in the communication buffer, output character string "BUFFRESET" to relevant communication port.

Example)

When clearing the communication buffer of the COM1 port:

PRINT COM1, "BUFFRESET"

3.2 Programming Examples for Communication with a Robot Language Program

It is possible to utilize communication functions in a robot language program in order to do such things as specify program branches, correct the position of the robot to be performed, etc. Listed below are several programming examples showing how to do this.

3.2.1 Program Branching

The INPUT command can be utilized to specify the number of times a certain action is to be repeated, to select a task for execution, etc.

Example 1)

Specifying the number of times an action is to be repeated

PROGRAM REPEAT

N=0

START:

PRINT COM1, "REQ"

INPUT COM1, N

IF N == 0 THEN GOTO START

FOR K = 1 TO N

MOVE A1

MOVE A2

. . .

NEXT K

PRINT COM1, "END"

END


In this program, the robot will repeat a certain series of motions as many times as the external device tells it to.

First, the controller will send the character string REQ to the external device. The external device will reply by sending back the number of times the operation is to be repeated.

The controller will read in this number as the variable N, and will use this variable in the FOR statement.

Without the IF statement, should the program execution have been suspended while the controller was waiting for data to come in, the variable N would be(mistakenly) taken as 0 when the program is resumed. However, the IF construction prevents this value from being used in the FOR loop by asking the external device for a retransmission. When the task is completed, the controller will send the character string END to the external device.

Data exchange



Example 2)


Selecting a task to be performed

PROGRAM SELECT K = 0START: PRINT COM1, "STR" SELECT: INPUT COM1, K GOTO(K) L1, L2, L3 PRINT COM1, "NG" **GOTO FIN** L1: (Task 1) **GOTO FIN** L2: (Task 2) **GOTO FIN** L3: (Task 3) **GOTO FIN** FIN:

END

In this program, the external device tells the controller what task is to be performed. First, the controller will send the character string STR to the external device. The external device will send back a number which specifying task the controller (robot) is to perform. The controller reads in this number as variable K, which is then used in the GOTO statement to branch the program to the appropriate task. Task 1 will be performed if the value of K is 1, Task 2 if the value is 2, and Task 3 if the value is 3. If the value of K is anything else, the controller will send the character string NG (non-acknowledge) back to the external device. Should program execution have been suspended while the controller was waiting for the number to come in, variable K will be taken as 0 when the program is resumed. In this case also, the controller will send the character string NG back to the external device.

Data exchange



3.2.2 Correcting the Position of the Robot


Data received from the host computer (upper level computer) can be used to correct the position of the robot.

Example 1)

PROGRAM SELECT
X = 0.0
Y = 0.0
Z = 0.0
C = 0.0
T = 0.0
PRINT COM1, "REQ"
INPUT COM1, X, Y, Z, C, T, SUM
IF SUM == $X + Y + Z + C + T + 1$
THEN GOTO ACTION
PRINT COM1, "NG"
GOTO FIN
ACTION:
PRINT COM1, "OK"
P1 = POINT(X, Y, Z, C, T)
MOVE P1
FIN:
END

In this program, the controller moves the robot to a position specified by the external device. The controller sends the character string REQ to the external device. The external device will respond by sending back the values for positional data X, Y, Z, C and T, and also the sum of these values plus 1 (as check-sum data). The controller will then see if the received data is correct by adding all the positional data, adding 1 to the result, and determining if check-sum value. If it does agree, the controller judges that the transmission was correctly received and sends back the character string NG. Assuming that the transmission was correctly received, the controller will create point P1 using that data and then tell the robot to move to that point.

Data exchange



Example 2)

Specifying a relative position

PROGRAM RELATIV

X = 0.0Y = 0.0

SUM = 0.0

MOVE P1

PRINT COM1, "REQ"

INPUT COM1, X, Y, SUM

IF SUM == X + Y + 1 THEN GOTO

ACTION

PRINT COM1, "NG"

GOTO FIN

ACTION:

PRINT COM1, "OK"

MOVE P1 + POINT (X, Y)

FIN:


END

In this program, the controller moves the robot to a location specified by the external device.

The controller sends the character string REQ to the external device. The external device will respond by sending back the values for coordinate positions X and Y, and also the sum of these values plus 1 (as check-sum data). The controller will then see if the received data is correct by adding X and Y, adding 1 to the result, value agrees with the check-sum value. If it does agree, the controller judges that the transmission was correctly received and sends back the character string OK to the external device. If it does not agree, the controller sends back the character string NG.

Assuming that the transmission was correctly received, the controller will add the X and Y values of the transmission to the X and Y values of Point P1 and make the robot move to the new position thus created.

Data exchange



Section 4

Host Port Communication

4.1 Transmission Protocol

The HOST port is positioned between the host computer and robot controller. After the controller power is turned on, the port waits for requests from the host computer. Basically, the host computer is a master station and the robot controller is a slave station. The robot controller sends back necessary data to the host computer in reply to commands reached from the host computer.




Fig. 4.1 Basic communication

Should the robot controller return an NG (Non-acknowledge) code in response to a command from the host computer, or should the robot controller give no response at all, resend the command from the host computer. Even should an error have occurred while transmitting a file, resend the file upload (or download) command from the host computer.


Furthermore, after receiving text from the controller, insert a delay of about 50 msec before beginning to transmit subsequent text from the host computer.

4.2 Transmission Format

Transmissions are made with the text unit shown below. A maximum of 253 bytes of actual data can be transmitted as a single text. Actual data in amounts over 253 bytes will be transmitted in one of the following two ways.

- (1) Files (robot programs, positional data, parameters) will be broken down into multiple texts and transmitted as described in Para. 4.3.3. The receiving station will send an answer signal back for each block of text transmitted. File upload (or download) commands are not necessary to transmit the second and following blocks of text.
- (2) Messages will be sent with multiple transmissions. In other words, the data will be broken down into multiple texts and each text will be transmitted independently. The station that received the data will reconstruct the multiple texts back into a single message.

4.2.1 Text




Text length: Max. 255 byte from STX through ETX

Text content:

- STX Start of text code (02H) 1 byte
- DATA Data section (Max. 253 bytes)
- ETX End of text code (03H) 1 byte

4.2.2 Data Section Format

The basic format of a text block is shown below.



(1) Command

Command consists of two alphabetical letters which signify the type of command. See Table 3.1 for command names and descriptions.

(2) Operand

The form of the operand varies depending on the type of command. For more information, read the description for the command in question.

(3) Characters

The characters to be used should be ASCII code alphanumeric characters and symbols.

Alphanumeric characters:

Special symbols:

4.3 Commands

4.3.1 List of Commands

Commands which may be used with this communication protocol are shown in Tables 4.1 and 4.2.

Table 4.1 List of commands (Host computer → Controller)

1 2 3	RN SP BR	Start Stop	Automatic operation	RN	
	BR	Stop			
3				SP	
		Servo OFF		BR	
4	SO	Servo ON		SO	
5	RS	Reset	Program reset	RS, PRG	
			Step reset	RS, STP	
			Cycle reset	RS, CYC	
			Output signal reset	RS, SIG	
			Select reset	RS, SEL	
6	SL	Program selection		SL, File name	
7	UL	File name	RAM file upload	UL, File name	
8	DL	File name	RAM file download	DL, File name	
9	CA	Directory	Directory request	CA	
10	SU	Status	Status request	SU	
11	EU	Error information	Error history upload	EU	
12	ER	File erase		ER, File name	
13	FL	File		FL, File contents	
14	OK	Acknowledge		OK	
15	NG	Non-acknowledge		NG	
16	EC*	Internal command	Internal command transmit	EC, Internal command	
17	MD	Guide mode setting	Guide mode setting	MD, <u>Guide mode</u>	
18	RT	Guide rate setting	Guide rate setting	RT, Guide rate	
19	SC	Guidance coordinate setting	Manual guidance coordinate system setting	SC, <u>Guidance</u> <u>coordinate</u>	
20	MW	Variable write	Global-defined variable write	MR, <u>Flag Name</u> , <u>Type</u> <u>Data</u>	
21	FD	Feed hold	Feed hold	FD	
22	SF	System total status	Request for fast-speed status information	SF	
23	MR	Variable read	Global-defined variable read	MR, <u>Name, Type</u>	
24	IVV	I/O write	I/O forced-writing	IW, Line No., Status	

No.	Command	Descriptions	Details	Text
25	VR	Version read	Robot and software version	VR
26	DO	Execution of DO statement	Execution of DO statement	DO, Statement

- * The internal commands executable by the EC command are as follows:
 - (1) MODE
 - (2) OVRD
 - (3) BREAK

Table 4.2 List of commands (Controller \rightarrow Host computer)

No.	Command	Descriptions	Details	Text
1	FL*	File		FL, File contents
2	OK	Acknowledge		OK
3	NV	Non-acknowledge		NG

- * The following files can be sent with the FL command.
 - (1) RAM files
 - User file (program and position data)
 - Parameter file
 - (2) File directories
 - (3) Status files
 - (4) Error history files
 - (5) System total status files
 - (6) Version information files
 - (7) Variable read data files

4.3.2 Commands and Operation Modes

Table 4.3 shows the operation modes in which each command is operative.

Table 4.3 Commands and valid operation modes

[Host computer → controller]

		Operation mode				
Command	Descriptions	Teach	External automatic (HOST)		Internal/external automatic (SIG)	
			ON	OFF	ON	OFF
RN	Automatic operation start	Χ	Х	0	Х	Х
SP	Stop	Х	0	Х	Х	Х
BR	Servo OFF	Χ	0	0	Х	Х
SO	Servo ON	Χ	Х	0	Х	Х
RS	Program reset	X	Х	0	Х	Х
	Step reset	Х	Χ	0	Х	Х
	Cycle reset	Х	Х	0	Х	Х
	Output signal reset	Х	Х	0	Х	Х
	Select reset	Х	Χ	0	Х	Х
SL	Program selection	Х	Х	0	Х	Х
UL	RAM file upload	Χ	Х	0	Χ	0
DL	RAM file download	Χ	Х	0	Х	0
CA	Directory request	0	0	0	0	0
SU	Status request	0	0	0	0	0
ER	File erase	Χ	Х	0	Χ	0
EU	Error history upload	0	0	0	0	0
EC	Internal command	Χ	0	0	Χ	Х
MD	Guide mode	Χ	Х	0	Χ	Х
RT	Guide rate	Х	Х	0	Х	Х
SC	Guidance coordinate setting	Χ	Х	0	Χ	Х
MW	Variable write	0	0	0	0	0
FD	Feed hold	Χ	0	0	Χ	Х
SF	System total status	0	0	0	0	0
MR	Variable read	0	0	0	0	0
I/W	I/O write	Χ	X	0	Χ	0
VR	Version read	0	0	0	0	0
DO	Execution of DO statement	Х	Х	0	Х	Х

Commands transmitted from the host computer to the controller can be received by the controller in the modes marked " μ ".

Commands transmitted from the controller to the host computer can be transmitted by the controller in the mode marked " μ ".

Note: In the external automatic (HOST) mode, all external control input signals are invalid except for the following signals.

Slow speed command

Servo ON

Servo OFF

Emergency stop

For details, see the Interface Manual.

4.3.3 Details of Commands

: Automatic Operation Start (Host computer → controller) RN


Format

RN (CR

Description

The RN (Automatic Operation Start) command is a command given by the host computer to the controller telling the controller to start up the program. If, after stopping the robot with the SP (Automatic Operation Stop) command, one sends the RN command again, the robot will start up from the step immediately following the step at which it was stopped.

Protocol



Note

If the power is turned on while the controller is set for the host mode (i.e., when the master mode switch on the controller panel is set to EXT), the operation mode of the system will be the cycle operation mode. If the controller is changed over to the host mode from the internal automatic mode (i.e., when the master mode switch is changed from INT to EXT), the operation mode of the system will be that in effect beforehand.


: Automatic Operation Stop (Host computer \rightarrow Controller) SP

Format SP (CR)

Description

The SP (Automatic Operation Stop) command is a command given by the host computer to the controller telling the controller to stop automatic operation. Also, this command informs the host computer when the controller is stopped (i.e., in the stop state). Furthermore, should the robot be stopped in accordance with any request other than that made by the host computer, this command will automatically be sent from the controller to the host computer.

Protocol




 $\hbox{: Servo OFF} \qquad \qquad \hbox{(Host computer} \, \to \, \hbox{Controller)} \quad \, \hbox{BR}$

Format BR (CR)

Description

The BR (Servo OFF) command is a command given by the host computer to the controller telling the controller to turn off the servo power.




: Servo ON (Host computer \rightarrow Controller) SO

Format SO (CR

Description

The servo ON command is given from the host computer to the controller to turn the power on.



: Reset (Host computer → Controller) RS

Format

RS, XXX (C

XXX: PRG Reset all program data (internal data)

STP Reset the program back to Step 1.

CYC Reset the program back to the step marked by the label RCYCLE.

SIG Turns off the digital output signals (DO1 to DO16) available to the user.

SEL Resets the execution file.

Description

The RS command will not be accepted unless the system is in a stop mode. The list of possible suffixes to the command is presented below.

(1) PRG

PRG will reset the program to Step 1. All program data will be initialized.

(2) STP

STP will reset the program to Step 1. All program data (such as variables) will remain unchanged.

(3) CYC


CYC will reset the program to the step marked by the label RCYCLE. All program data will remain unchanged.

(4) SIG

SIG will put the digital outputs (DO1 to DO16) in the non-active state.

(5) SEL

SEL will reset the execution file.



: Program Selection

 $(\text{Host computer} \, \to \, \text{Controller})$


SL

Format

SL, file name (CR

Description

The SL command selects a program to be executed under automatic operation.



UL

: File Upload Request


(Host computer → Controller)

Format

UL, file name (CR

Function

The UL command is used to upload (transmit) a specified file from the controller RAM drive to the host computer. For information on the contents of files to be uploaded, see the FL (File) command.



Note

DL


: File Download Request \qquad (Host computer \rightarrow Controller)

Format

DL, file name (CR

Function

The DL command is used to download (transmit) a specified file from the host computer to the controller RAM drive. For information on the contents of files to be downloaded, see the FL (File) command.



Note


: File Directory Request (Host computer → Controller) CA

Format CA (CR

Function

The CA command is used to transmit the directory of files in the RAM drive from the controller to the host computer. For information on the contents of directories to be transmitted, see the FL (File) command.

Protocol



: Status Request (Host computer → Controller) SU
 : System total status request (Host computer → Controller) SF

Format


SU (CR) Status information

SF (CR) System total status information

Function

The SU command is used to send the internal status (state) of the controller to the host computer. For information on the contents of status file to be transmitted, see the FL (File) command.

Protocol



: Error History Request (Host computer \rightarrow Controller) EU


Format

EU (CR)

Function


The EU command is used to send the controller error history data to the host computer. For information on the contents of error history files to be transmitted, see the FL (File) command.

Protocol



Note

: File Erase (Host computer \rightarrow Controller) ER **Format** ER, file name (CR Description The ER command is used to erase a specified file from the controller RAM drive.



IW

: I/O Write (Host computer → Controller)

Format


IW, Line No. ON/OFF command



Function


The IW command is used to instruct forced writing of up to 32 I/Os from the host computer to the controller. For the ON/OFF command, specify "0" for OFF and "1" for ON.

Controller Host computer IW. Line No. ON/OFF command CR Normal response OK CR Normal response (2) Error (Request cannot be accepted) NG CR Request cannot be accepted.



The VR command is used to send the system version information to the host computer.

For details on the version information, see the file (FL) command.



: Execution of DO statement (Host computer → Controller) DO

Format

DO, Command statement (




Function

The DO command is used to directly execute a command from the host computer.

For details on the command, see the Robot Language Manual.

In the feed hold status or servo power OFF status, negative response NG is sent back from the controller.



: Variable read (Host computer → Controller) MR

Format

MR, Variable name Variable type



Function

The MR command is used to transfer the read data of global-defined variable to the host computer. Each variable name should consist of up to ten (10) characters.

For the array variable, specify the array elements ("Variable name (*, *, ...)").

Specify one of the following numbers for the variable type data.

0 : Integer type 5 : Array integer type


1 : Real number type 6 : Array real number type

2 : Load type 7 : Array load type

3 : Coordinate type4 : Position type8 : Array coordinate type9 : Array position type

-1: Unclarified

For details of the read data, see the file (FL) command.



: Guide mode setting

(Host computer → Controller)

MD

Format

MD, Guide mode



Function

The MD command is used to instruct the guide mode setting from the host computer to the controller.


The guide mode can be specified as shown below.

0 : Jog

1 : Inching

2 : Free

In a status other than the program stop status in the external automatic mode, negative response NG is sent back.



: Guide rate setting

(Host computer → Controller)

RT

Format

RT, Guide rate


Function

The RT command is used to instruct the guide rate setting from the host computer to the controller.

The guide rate can be specified as shown below.

0 : Slow1 : Mid2 : Fast

In a status other than the program stop status in the external automatic mode, negative response NG is sent back.



: Guidance coordinate setting (Host computer \rightarrow Controller) SC

Format

SC, Guidance coordinate




Function

The SC command is used to instruct the guidance coordinate system setting from the host computer to the controller.

The guidance coordinate system can be specified as shown below.

0 : Joint1 : Tool2 : Work3 : World

In a status other than the program stop status in the external automatic mode, negative response NG is sent back.



: Write global variable (HOST ___ CNTL) MW

Format

MW, Flag _ Variable name _ Variable type _ Write data ... (CR

Descriptions

This function requests writing of data into the user's defined variable.

The flag is a control flag for restoring or non-restoring of data in the program file, as shown below.

Flag	Description
0	Restoring of data in the program file is not executed.
1	Restoring of data in the program file is executed.

The variable name should consist of up to ten (10) characters. Specify the array element ("Variable name (*, *, \cdots)") for the array variable.

Specify the variable type data and write data in the following manner.

Variable type	Variable type data	Write data		
Integer type 0		1 pc. (long)		
Real number type	1	1 pc. (float)		
Load type	2	2 pcs. (float _ float)		
Coordinate type	3	4 pcs. (float _ float _ float)		
Position type	4	6 pcs. (float _ float _ float _ float _ float _ float)		
Array integer type	5	1 pc. (long)		
Array real number type	6	1 pc. (float)		
Array load type	7	2 pcs. (float _ float)		
Array coordinate type	8	4 pcs. (float _ float _ float)		
Array position type	9	6 pcs. (float _ float _ float _ float _ float)		

Controller

Host computer

MW, Flag Variable name Variable type Write data CR

(1) Normal finish OK CR

(2) Abnormal finish NG CR


Request cannot be accepted. (Absence of variable name, abnormal data)

: Feed hold (Host computer → Controller) FD

Format

FD CR

The FD command is used to inform from the host computer to the controller that the FEED HOLD pushbutton switch has been pressed.



: Acknowledge	$(Host\;computer \leftrightarrow Controller)$	OK
Format OK CR		
Description		
The OK (Acknowledge) commar	nd indicates an affirmative response	ı

: Non-acknowledge	$(Host\ computer \leftrightarrow Controller)$	NG
Format NG (CR)		
Description		
The NG (Non-acknowle	dge) command indicates a negative response.	

: Internal Command Execution

(Host computer \rightarrow Controller)

EC

Format

EC (CR

Description

The internal command can be executed from the host computer.

The executable internal commands are as follows.

 $MODE\theta CONT$

MODEθCYCLE


MODEθSTEP

MODEθSEG

OVRDθSet value (1 ~ 100)

BREAK

Note: " θ " signifies a space.



: File (Host computer \leftrightarrow Controller) FL

Format

FL, file contents EOF

 When the amount of data to be transmitted exceeds 251 (253) bytes (the maximum amount of data for one text), the data is broken down into additional texts (as shown below) before being transmitted.

ritents 2 File contents 3 EOF	File contents 2	L, file contents 1	FL,
-------------------------------	-----------------	--------------------	-----

- EOF (End of File) is a 1 byte code (1AH) used to mark the end of the file.
- The STX (start), ETX (stop) and SUM (check-sum) bytes are attached to each text. (The SUM byte is only appended when check-sum has been specified.)

Descriptions

The FL command is used as a response command to the command given beforehand.

File types and contents

1.1 Types


Description	Corresponding command
RAM file	UL, DL
File directory	CA
Status	SU
Error history	EU
System total status	SF
Version information	VR
Memory read data	MR

1.2 File contents

A file is composed of one or more records. Different kinds of files are made up of different kinds of records, each of which is shown below.

Furthermore, in the tables below, the value in the Size column is the maximum size of the data section. "Fixed" means that the length of the data section is fixed; "Variable" means that the length is variable.

(1) RAM file




Record structure

No.	Name	Size(byte)	Description
1	Character data	Max 252 (Variable)	ASCII code alphanumeric characters and symbols
2	CR	1 (Fixed)	0DH(Record termination code)

This record corresponds to one line of a program or one line of positional data.

For information on file structure, see Para. 4.4, "RAM Files."



(2) User file directory

Record structure

No.	Name	Size(byte)	Description
1	File name	12(Variable)	File name in alphanumeric characters beginning with an alphabetic character.
2	Size	5(Variable)	Size of file in bytes.
3	Attribute	-(Variable)	Shows the attribution. The attribute is omitted if the attribution is not specified.
4	CR	1(Fixed)	0DH (Record termination code)


(3) Status file

Mode	Ш	File name	Speed override	Ш	Speed limit	:	
					Machine status	Ш	Execution status

No.	Name	Size(byte)	Description		
1	Mode	30	The controller mode is shown in the following format:		
		(Variable)		(operation mode)"	
			(1) MODE :	5 byte fixed length.	
			(2) (mode) :	Controller mode	
			"external (sig)"	: External Automatic Mode	
			CALCITICI (SIG)	(External Operation Signal Mode)	
			"external (host	: External Automatic Mode	
			external (1103t	(Host Mode)	
			"internal"	: Internal Operation Mode	
			"teaching"	: Test run mode	
			(3) /	: 1 byte fixed length.	
			(4) (Operation Mode)	: Automatic Operation Modes	
			"step"	: Step Operation Mode	
			"continuous"	: Continuous Operation Mode	
			"cycle"	: Cycle Operation Mode	
			"segment"	: Segment operation mode	
2	File	17	The format of the	e presently selected file is as follows.	
	name	(Variable)	"FILE : (File nam	ne)"	
			(1) FILE	: 5 byte fixed length.	
			(2) (File name)	: Name of the file that has been	
			(2) (File name)	selected.	
3	Speed	11	The speed overr	ide is shown in the following format.	
	override	(Variable)	"OVRD : (Overri	de) %"	
			(1) OVRD	: 5-byte fixed length.	
			(2) (Override)	: Percentage for the speed override.	
			(3) %	: 1 byte fixed length.	

No.	Name	Size (byte)		Description	
4	Re-serv	11	The speed limit is shown in the following format.		
	ed	(Variable)	"LSPEED : (limit) %"		
	(Speed	,	(1) LSPEED	: 7 byte fixed length.	
	limit)		(2) (Limit)	: Percentage for the speed limit.	
			(3) %	: 1 byte fixed length.	
5	Machine	12	The machine s	status is shown in the following format.	
	status	(Variable)	"MACHINE : (s	status)"	
			(1) MACHINE	: 8 byte fixed length.	
			(2) (Status)	: Robot status	
				: Status in which machine lock has	
			"free"	been	
			nee	rescinded.	
				(Status in which the robot can move.)	
				: Status in which machine lock is in	
			"lock"	effect.	
			IOCK	(Status in which the robot cannot	
				move.)	
6	Exe-cutio	21	The execution status is shown in the following format.		
	n	(Variable)	"STATUS : (E)	recution status)"	
	status		(1) STATUS	: 7 byte fixed length.	
			(2) (Execution status)	: Operating state of the robot.	
			"running"	: In Automatic Operation	
				: In Stop (Initialized Mode)	
			"stop (Reset)" (Same status as that for program	
				Reset)	
				: In Stop (Retry Mode) (Restart	
			"Stop (Retry))" operation from the interrupted	
				movement.)	
			"Stop	: In Stop (Continuous Mode)	
			(continue)"	(Continue program from the present	
			(continue)	step.)	

(4) Error history file



No.	Name	Size(byte)	Description		
1	Size	2 (variable)	Number (in base 10) of error histories.		
			Placed only at the beginning of the file.		
2	Error	7 (Fixed)	The error code of an error which occurred is shown in		
	code		the following format.		
			"XXX-YYY"		
			XXX : Main code		
			YYY : Sub code		
			For more information on errors, see the "Operator's		
			Manual."		
3	Date	8 (Fixed)	The date on which the error occurred is shown in the		
			following format.		
			"YY-MM-DD"		
			YY : Year (Last tow numbers only)		
			MM : Month		
			DD : Day		
4	Time	8 (Fixed)	The date on which the error occurred is shown in the		
			following format.		
			"HH:SS:MM"		
			HH : Hours (In 24-hour"military time.")		
			MM : Minutes		
			SS : seconds		
5	CR	1 (Fixed)	0DH (Record termination code)		

(5) System total status

The following information is transmitted as the system total status information in the binary notation (250 bytes).

Motion status	I/O information	Current value data		
52 bytes	64 bytes/	134 bytes		

Detailed data of each group are tabled below.

I) Motion status

No.	Name	Size (byte)	Description		
1	Servo power status	1	0: OFF, 1: ON		
2	EMERGENCY stop switch status	1	0: OFF, 1: ON		
3	Motion status	1	0: Stop (reset)		
			1: Run		
			2: Stop (retry)		
			3: Stop (cont)		
4	SU command request	1	0: Without request, 1: With request		
5	Current alarm	2×10 pcs.	Error of level 8: 0 ~ 367		
	information		Error of level 4: 368 ~ 511		
			Error of level 2: 512 ~ 735		
			Error of level 1: 736 ~ 895		
			Other than above: No error		
6	Program execution line	2	Line number during program execution.		
7	Program analysis line	2	Line number during program analysis.		
8	Program execution task	2	Task number during program execution.		
9	Program analysis task	2	Task number during program analysis.		
10	Feed hold status	2	0: OFF, 1: ON		
11	Guidance coordinate system status	2	0: Joint, 1: Tool, 2: Work, 3: World		
12	Guide rate status	2	0: Slow, 1: Mid, 2: Fast		
13	Guide mode status	2	0: Jog, 1: Inching, 2: Free		
14	Master mode status	2	0: Teaching mode, 1: Internal mode 2: EXT (SIG) mode, 3: EXT (HOST) mode		
15	Dummy	2	Reserved		
16	Power ON time	4	Unit: Min.		
17	Program run time	4	Unit: Min.		
	Total	52			

II) I/O information

No.	Name	Size (byte)	Description			
1	General input 1	2	VIData[0]			
			Bit	Line No.	Signal name	
			0	Din1	General input	
			1	Din2	General input	
			2	Din3	General input	
			3	Din4	General input	
			4	Din5	General input	
			5	Din6	General input	
			6	Din7	General input	
			7	Din8	General input	
			8	Din9	General input	
			9	Din10	General input	
			10	Din11	General input	
			11	Din12	General input	
			12	Din13	General input	
			13	Din14	General input	
			14	Din15	General input	
			15	Din16	General input	
2	Conoral innut 2	2	\/IDoto[4]	1		
2	General input 2	2	VIData[1]	Line No.	Cianal nama	
			0	Din17	Signal name General input	
				Din17	•	
			2		General input	
				Din19	General input	
			3	Din20	General input	
			4	Din21	General input	
			5	Din22	General input	
			7	Din23	General input	
				Din24	General input	
			8	Din25	General input	
			9	Din26	General input	
			10	Din27	General input	
			11	Din28	General input	
			12	Din29	General input	
			13	Din30	General input	
			14	Din31	General input	
			15	Din32	General input	

No.	Name	Size (byte)	Description		
3	General input 3	2	VIData[2]		
	·		Bit	Line No.	Signal name
			0	Din33	General input
			1	Din34	General input
			2	Din35	General input
			3	Din36	General input
			4	Din37	General input
			5	Din38	General input
			6	Din39	General input
			7	Din40	General input
			8	Din41	General input
			9	Din42	General input
			10	Din43	General input
			11	Din44	General input
			12	Din45	General input
			13	Din46	General input
			14	Din47	General input
			15	Din48	General input
4	General input 4	2	VIData[3] Bit Line No. Signa		Signal name
			0	Din49	General input
			1	Din50	General input
			2	Din51	General input
			3	Din52	General input
			4	Din53	General input
			5	Din54	General input
			6	Din55	General input
			7	Din56	General input
			8	Din57	General input
			9	Din58	General input
			10	Din59	General input
			11	Din60	General input
			12	Din61	General input
			13	Din62	General input
			14	Din63	General input
			15	Din64	General input
					_

No.	Name	Size (byte)		Description		
5	Extension input 1	2	VIData[4]			
	•			Bit	Line No.	Signal name
				0	Din101	Extension input
			:	1	Din102	Extension input
				2	Din103	Extension input
				3	Din104	Extension input
			•	4	Din105	Extension input
				5	Din106	Extension input
				6	Din107	Extension input
				7	Din108	Extension input
				8	Din110	Extension input
				9	Din110	Extension input
				10	Din111	Extension input
				11	Din112	Extension input
				12	Din113	Extension input
				13	Din114	Extension input
				14	Din115	Extension input
				15	Din116	Extension input
6	Extension input 2	2	V	/IData[5]	Line No.	Signal name
				0	Din117	Extension input
				1	Din118	Extension input
				2	Din119	Extension input
				3	Din120	Extension input
				4	Din121	Extension input
				5	Din122	Extension input
				6	Din123	Extension input
			•	7	Din124	Extension input
			:	8	Din125	Extension input
				9	Din126	Extension input
				10	Din127	Extension input
				11	Din128	Extension input
				12	Din129	Extension input
				13	Din130	Extension input
				14	Din131	Extension input
				15	Din132	Extension input

No.	Name	Size (byte)		Desc	ription
7	Extension input 3	2	VIData[6	6]	
	'		Bit	Line No.	Signal name
			0	Din133	Extension input
			1	Din134	Extension input
			2	Din135	Extension input
			3	Din136	Extension input
			4	Din137	Extension input
			5	Din138	Extension input
			6	Din139	Extension input
			7	Din140	Extension input
			8	Din141	Extension input
			9	Din142	Extension input
			10	Din143	Extension input
			11	Din144	Extension input
			12	Din145	Extension input
			13	Din146	Extension input
			14	Din147	Extension input
			15	Din148	Extension input
8	Extension input 4	2	VIData[7	7]	
			Bit	Line No.	Signal name
			0	Din149	Extension input
			1	Din150	Extension input
			2	Din151	Extension input
			3	Din152	Extension input
			4	Din153	Extension input
			5	Din154	Extension input
			6	Din155	Extension input
			7	Din156	Extension input
			8	Din157	Extension input
			9	Din158	Extension input
			10	Din159	Extension input
			11	Din160	Extension input
			12	Din161	Extension input
			13	Din162	Extension input
			14	Din163	Extension input
			15	Din164	Extension input
				<u> </u>	

No.	Name	Size (byte)		Desc	ription
9	System input 1	2	VIData[8]		
			Bit	Line No.	Signal name
			0	Din201	Hand input
			1	Din202	Hand input
			2	Din203	Hand input
			3	Din204	Hand input
			4	Din205	Hand input
			5	Din206	Hand input
			6	Din207	Hand input
			7	Din208	Hand input
			8	Din210	
			9	Din210	
			10	Din211	
			11	Din212	
			12	Din213	
			13	Din214	
			14	Din215	
			15	Din216	
10	System input 2	2	VIData[9]		
			Bit	Line No.	Signal name
			0	Din217	Alarm of level 8
			1	Din218	Alarm of level 8
			2	Din219	Alarm of level 8
			3	Din220	Alarm of level 8
			4	Din221	Alarm of level 4
			5	Din222	Alarm of level 4
			6	Din223	Alarm of level 4
			7	Din224	Alarm of level 4
			8	Din225	Alarm of level 2
			9	Din226	Alarm of level 2
			10	Din227	Alarm of level 2
			11	Din228	Alarm of level 2
			12	Din229	Alarm of level 1
			13	Din230	Alarm of level 1
			14	Din231	Alarm of level 1
			15	Din232	Alarm of level 1
1			I -		

System input 3	2						
•	_	V	VIData[10]				
			Bit	Line No.	Signal name		
			0	Din233	JOGmove		
			1	Din234	JOGinching		
			2	Din235	JOGspeed		
			3	Din236	JOGcood		
			4	Din237	JOF+-		
			5	Din238	JOGaxis1		
			6	Din239	JOGaxis2		
			7	Din240	JOGaxis3		
			8	Din241			
			9	Din242			
			10	Din243			
			11	Din244			
			12	Din245			
			13	Din246			
			14	Din247			
			15	Din248			
System input 4	2	٧		_			
					Signal name		
					STROBE		
					PRG_RST		
					STEP_RST		
					CYC_RST		
					DO_RST		
					ALM_RST		
					RUN		
					EX_SVON		
					STOP		
					CYCLE		
					LOW_SPD		
					BREAK		
					SVOFF		
					I_TEACH		
			15	Din264			
	System input 4	System input 4 2	System input 4 2 V	3 4 5 6 7 8 9 10 11 12 13 14 15	3 Din236 4 Din237 5 Din238 6 Din239 7 Din240 8 Din241 9 Din242 10 Din245 13 Din246 14 Din247 15 Din248 System input 4 2 VIData[11]		

No.	Name	Size (byte)			Desc	ription
13	Field bus input 1	2	V	'IData[12	2]	
	·			Bit	Line No.	Signal name
				0	Din301	Field bus input
				1	Din302	Field bus input
				2	Din303	Field bus input
				3	Din304	Field bus input
				4	Din305	Field bus input
				5	Din306	Field bus input
				6	Din307	Field bus input
				7	Din308	Field bus input
				8	Din310	Field bus input
				9	Din310	Field bus input
				10	Din311	Field bus input
				11	Din312	Field bus input
				12	Din313	Field bus input
				13	Din314	Field bus input
				14	Din315	Field bus input
				15	Din316	Field bus input
14	Field bus input 2	2		All Data [13] Bit 0 1 2 3 4 5 6 7 8 9 10 11 12	Line No. Din317 Din318 Din319 Din320 Din321 Din322 Din323 Din324 Din325 Din326 Din327 Din328 Din329	Signal name Field bus input
				13	Din330	Field bus input
				14	Din331	Field bus input
				15	Din332	Field bus input

No.	Name	Size (byte)			Desc	ription
15	Field bus input 3	2	٧	'IData[1	4]	
	·			Bit	Line No.	Signal name
				0	Din333	Field bus input
			•	1	Din334	Field bus input
				2	Din335	Field bus input
			-	3	Din336	Field bus input
			-	4	Din337	Field bus input
				5	Din338	Field bus input
				6	Din339	Field bus input
			İ	7	Din340	Field bus input
				8	Din341	Field bus input
				9	Din342	Field bus input
				10	Din343	Field bus input
				11	Din344	Field bus input
				12	Din345	Field bus input
				13	Din346	Field bus input
			1	14	Din347	Field bus input
			1	15	Din348	Field bus input
16	16 Field bus input 4	2		/IData[18 Bit 0 1 2 3 4	5] Line No. Din349 Din350 Din351 Din352 Din353	Signal name Field bus input
			-	5	Din354	Field bus input
				6	Din355	Field bus input
				7	Din356	Field bus input
				8	Din357	Field bus input
				9	Din358	Field bus input
				10	Din359	Field bus input
				11	Din360	Field bus input
				12	Din361	Field bus input
				13	Din362	Field bus input
				14	Din363	Field bus input
				15	Din364	Field bus input
			1			

No.	Name	Size (byte)			Desc	ription
17	General output 1	2	٧	OData[0]	
				Bit	Line No.	Signal name
			:	0	Dout1	General output
				1	Dout2	General output
			•	2	Dout3	General output
			•	3	Dout4	General output
				4	Dout5	General output
				5	Dout6	General output
				6	Dout7	General output
				7	Dout8	General output
				8	Dout9	General output
				9	Dout10	General output
				10	Dout11	General output
				11	Dout12	General output
				12	Dout13	General output
				13	Dout14	General output
				14	Dout15	General output
				15	Dout16	General output
18	General output 2	2	٧	'OData[, -	
				Bit	Line No.	Signal name
				0	Dout17	General output
				1	Dout18	General output
				2	Dout19	General output
				3	Dout20	General output
				4	Dout21	General output
				5	Dout22	General output
				6	Dout23	General output
				7	Dout24	General output
				8	Dout25	General output
				9	Dout26	General output
				10	Dout27	General output
				11	Dout28	General output
				12	Dout29	General output
				13	Dout30	General output
				14	Dout31	General output
				15	Dout32	General output

No.	Name	Size (byte)			Desc	ription
19	General output 3	2	VOD	ata[2	2]	
	·		В	Bit	Line No.	Signal name
			(0	Dout33	General output
			,	1	Dout34	General output
			2	2	Dout35	General output
			3	3	Dout36	General output
			4	4	Dout37	General output
				5	Dout38	General output
			6	6	Dout39	General output
			7	7	Dout40	General output
			8	8	Dout41	General output
			9	9	Dout42	General output
			1	0	Dout43	General output
			1	1	Dout44	General output
			1	2	Dout45	General output
			1	3	Dout46	General output
			1	4	Dout47	General output
			1	5	Dout48	General output
20	General input 4	2	(ata[3 Bit 0 1	Line No. Dout49 Dout50	Signal name General output General output
				2	Dout51	General output
				3	Dout52	General output
				4	Dout53	General output
				5	Dout54	General output
				6	Dout55	General output
				7	Dout56	General output
				8	Dout57	General output
				9	Dout58	General output
				0	Dout59	General output
				1	Dout60	General output
				2	Dout61	General output
			 	3	Dout62	General output
				4	Dout63	General output
1						
			1	5	Dout64	General output

No.	Name	Size (byte)			Desc	ription
21	Extension output 1	2	٧	OData[4	1]	
	•			Bit	Line No.	Signal name
				0	Dout101	Extension output
				1	Dout102	Extension output
				2	Dout103	Extension output
				3	Dout104	Extension output
				4	Dout105	Extension output
				5	Dout106	Extension output
				6	Dout107	Extension output
				7	Dout108	Extension output
				8	Dout110	Extension output
				9	Dout110	Extension output
				10	Dout111	Extension output
				11	Dout112	Extension output
				12	Dout113	Extension output
				13	Dout114	Extension output
				14	Dout115	Extension output
				15	Dout116	Extension output
22	Extension output 2	2	V	OData[5 Bit 0	Line No.	Signal name Extension output
				1	Dout118	Extension output
				2	Dout119	Extension output
			-			
				J	Dout120	Extension output
				3		Extension output Extension output
					Dout120 Dout121 Dout122	Extension output
			_	4	Dout121	
			_	4 5	Dout121 Dout122	Extension output Extension output
			_	4 5 6	Dout121 Dout122 Dout123	Extension output Extension output Extension output
				4 5 6 7	Dout121 Dout122 Dout123 Dout124	Extension output Extension output Extension output Extension output
				4 5 6 7 8	Dout121 Dout122 Dout123 Dout124 Dout125	Extension output Extension output Extension output Extension output Extension output
				4 5 6 7 8 9	Dout121 Dout122 Dout123 Dout124 Dout125 Dout126	Extension output Extension output Extension output Extension output Extension output Extension output
			-	4 5 6 7 8 9	Dout121 Dout122 Dout123 Dout124 Dout125 Dout126 Dout127	Extension output
				4 5 6 7 8 9 10	Dout121 Dout122 Dout123 Dout124 Dout125 Dout126 Dout127 Dout128	Extension output
				4 5 6 7 8 9 10 11	Dout121 Dout122 Dout123 Dout124 Dout125 Dout126 Dout127 Dout128 Dout129	Extension output
				4 5 6 7 8 9 10 11 12	Dout121 Dout122 Dout123 Dout124 Dout125 Dout126 Dout127 Dout128 Dout129 Dout130	Extension output

No.	Name	Size (byte)			Desc	ription
23	Extension output 3	2	V	OData[6	<u> </u>	
	·		Г	Bit	Line No.	Signal name
				0	Dout133	Extension output
				1	Dout134	Extension output
				2	Dout135	Extension output
				3	Dout136	Extension output
				4	Dout137	Extension output
				5	Dout138	Extension output
				6	Dout139	Extension output
				7	Dout140	Extension output
				8	Dout141	Extension output
				9	Dout142	Extension output
				10	Dout143	Extension output
				11	Dout144	Extension output
				12	Dout145	Extension output
				13	Dout146	Extension output
				14	Dout147	Extension output
				15	Dout148	Extension output
24	Extension output 4	2	V	OData[7	7] Line No.	Signal name
				0	Dout149	Extension output
				1	Dout150	Extension output
				2	Dout151	Extension output
				3	Dout152	Extension output
				4	Dout153	Extension output
			-	5	Dout154	Extension output
			-	6	Dout155	Extension output
				7	Dout156	Extension output
				8	Dout157	Extension output
				9	Dout158	Extension output
				10	Dout159	Extension output
				11	Dout160	Extension output
				12	Dout161	Extension output
				13	Dout162	Extension output
				14	Dout163	Extension output
				15	Dout164	Extension output
				. •		' '

No.	Name	Size (byte)		Desc	ription	
25	System output 1	2	VOData	[8]		
			Bit	Line No.	Signa	l name
			0	Dout201	Hand out	out
			1	Dout202	Hand out	
			2	Dout203	Hand out	
			3	Dout204	Hand out	out
			4	Dout205	Hand out	out
			5	Dout206	Hand out	out
			6	Dout207	Hand out	out
			7	Dout208	Hand outp	out
			8	Dout210		
			9	Dout210		
			10	Dout211		
			11	Dout212		
			12	Dout213		
			13	Dout214		
			14	Dout215		
			15	Dout216		
26	System output 2	2	VOData	[9]		
			Bit	Line No.	Signa	I name
			0	Dout217	Seq. para	meter
			1	Dout218	Seq. para	meter
			2	Dout219	Seq. para	meter
			3	Dout220	Seq. para	meter
			4	Dout221	Seq. para	meter
			5	Dout222	Seq. para	meter
			6	Dout223	Seq. para	meter
			7	Dout224	Seq. para	meter
					TS1000	TS2000
			8	Dout225		
			9	Dout226		
			10	Dout227		
			11	Dout228		
			12	Dout229		O13_SEL
			13	Dout230		O14_SEL
			14	Dout231		O15_SEL
			15	Dout232		O16_SEL

No.	Name	Size (byte)			Desc	ription			
27	System output 3	2	VOData[10]						
				Bit	Line No.	Signal name			
						TS1000	TS2000		
				0	Dout233	I9_SEL	I23_SEL		
				1	Dout234	I10_SEL	I24_SEL		
				2	Dout235	I11_SEL	I33_SEL		
				3	Dout236	I12_SEL	134_EL		
				4	Dout237	I13_SEL	I35_SEL		
				5	Dout238	I14_SEL	I36_SEL		
				6	Dout239	I15_SEL	I37_SEL		
				7	Dout240	I16_SEL	I38_SEL		
				8	Dout241	O9_SEL	O25_SEL		
				9	Dout242	O10_SEL	O26_SEL		
				10	Dout243	O11_SEL	O27_SEL		
				11	Dout244	O12_SEL	O28_SEL		
		_	12	Dout245	O13_SEL	O29_SEL			
			13	Dout246	O14_SEL	O30_SEL			
			14	Dout247	O15_SEL	O31_SEL			
				15	Dout248	O16_SEL	O32_SEL		
28	System output 4	2	٧	'OData[l1]				
			-	Bit	Line No.	Signal name			
				0	Dout249	EMG_ST			
				1	Dout250	SV_RDY			
				2	Dout251	ACK			
				3	Dout252	TEACH			
				4	Dout253	INT			
				5	Dout254	EXTSIG			
				6	Dout255	EXTHOST			
				7	Dout256	SYS_RDY			
				8	Dout257	AUTORUN			
				9	Dout258	CYC_END			
				10	Dout259	LOW_ST			
				11	Dout260	CYC_ST			
				12	Dout261	BT_ALM			
			-	13	Dout262	ALARM			
				14	Dout263				
				15	Dout264				
			'			•			


No.	Name	Size (byte)			Desc	ription
29	Field bus output 1	2	V	OData[1	[2]	
	•			Bit	Line No.	Signal name
				0	Dout301	Field bus output
				1	Dout302	Field bus output
				2	Dout303	Field bus output
				3	Dout304	Field bus output
				4	Dout305	Field bus output
				5	Dout306	Field bus output
				6	Dout307	Field bus output
				7	Dout308	Field bus output
				8	Dout310	Field bus output
				9	Dout310	Field bus output
				10	Dout311	Field bus output
				11	Dout312	Field bus output
				12	Dout313	Field bus output
				13	Dout314	Field bus output
				14	Dout315	Field bus output
				15	Dout316	Field bus output
30	Field bus output 2	2	V	OData[1	[3]	
				Bit	Line No.	Signal name
				0	Dout317	Field bus output
				1	Dout318	Field bus output
				2	Dout319	Field bus output
				3	Dout320	Field bus output
				4	Dout321	Field bus output
				5	Dout322	Field bus output
				6	Dout323	Field bus output
				7	Dout324	Field bus output
				8	Dout325	Field bus output
				9	Dout326	Field bus output
				10	Dout327	Field bus output
				11	Dout328	Field bus output
				12	Dout329	Field bus output
				13	Dout330	Field bus output
				14	Dout331	Field bus output
				15	Dout332	Field bus output

No.	Name	Size (byte)			Desc	ription					
31	Field bus output 3	2	VOData[14]								
				Bit	Line No.	Signal name					
				0	Dout333	Field bus output					
				1	Dout334	Field bus output					
				2	Dout335	Field bus output					
				3	Dout336	Field bus output					
				4	Dout337	Field bus output					
				5	Dout338	Field bus output					
				6	Dout339	Field bus output					
				7	Dout340	Field bus output					
				8	Dout341	Field bus output					
				9	Dout342	Field bus output					
				10	Dout343	Field bus output					
				11	Dout344	Field bus output					
				12	Dout345	Field bus output					
				13	Dout346	Field bus output					
				14	Dout347	Field bus output					
				15	Dout348	Field bus output					
32	Field bus output 4 2	2	VO	VOData[15]							
				Bit	Line No.	Signal name					
				0	Dout349	Field bus output					
				1	Dout350	Field bus output					
				2	Dout351	Field bus output					
				3	Dout352	Field bus output					
				4	Dout353	Field bus output					
				5	Dout354	Field bus output					
				6	Dout355	Field bus output					
				7	Dout356	Field bus output					
				8	Dout357	Field bus output					
				9	Dout358	Field bus output					
				10	Dout359	Field bus output					
				11	Dout360	Field bus output					
				12	Dout361	Field bus output					
				13	Dout362	Field bus output					
				14	Dout363	Field bus output					
				15	Dout364	Field bus output					

III) Current value data

No.	Name	Size (byte)	Description
1	Joint coordinate value	4 × 6 axes	As shown below, values are set in the order of axis 1 to axis 6.
2	World coordinate value	4 × 6 axes	Axis 1 (float)
3	Work coordinate value	4 × 6 axes	Axis 2 (float)
			Axis 3 (float)
			Axis 4 (float)
			Axis 5 (float)
			Axis 6 (float)
4	Work coordinate name	20	Name of work coordinate system
5	Tool coordinate name	20	Name of tool coordinate system
6	Base coordinate name	20	Name of base coordinate system
7	Reserved	2	
	Total	134	

(6) Version information



[Contents of record]

No.	Name	Size (byte)	Description
1	System name	10	
2	Date of creation (Year/Month/Day)	10	20**/**/**
3	Time of creation (Hour/Min)	5	**.**
4	Checksum	4	
5	CR	1	Record end code (0DH)

(7) Variable read data

Read data 1	u	Read data 2	u	Read data 3	U	

The variable read data differs as shown below with the type of variable.


Variable type data	Туре	Read data
0	Integer type	1 pc. (long)
1	Real number type	1 pc. (float)
2	Load type	2 pcs. (float ⊔ float)
3	Coordinate type	4 pcs. (float ⊔ float ⊔ float)
4	Position type	6 pcs. (float _ float _ float _ float _ float)
5	Array integer type	1 pc. (long)
6	Array real number type	1 pc. (float)
7	Array load type	2 pcs. (float loat)
8	Array coordinate type	4 pcs. (float _ float _ float)
9	Array position type	6 pcs. (float _ float _ float _ float _ float)

The float data is expressed by a value calculated to three decimal places.

4.4 Ram Files

4.5.1 User Files (Work files)

The user files store some programs and positional data.



As shown in the above figure, the main program or global variable data, subprograms, and data block, in which the positional data are described, are placed in that order. The delimiting codes for file names and programs and the check sum are not placed. At the end of each line, a carriage return code is placed. At the end of the file, an EOF code is placed.

The characters to be used should be ASCII code alphanumeric characters and symbols.

Alphanumeric characters:

```
a b c d e f g h i j k l m n o p q r s t u v w x y z A B C D E F G H I J K L M N O P Q R S T U V W X Y Z 0 1 2 3 4 5 6 7 8 9

Special symbols:

" ' ( ) + - * / , . < > = ! [ ] { } % ^ & ?
```

The robot controller does not distinguish between upper case and lower case characters. Do not use Chinese characters or double width characters. In particular, make sure that blanks are not double width characters. Moreover, do not place a tab code in the file.

(1) Global variable

The global variable area which can be referred from all programs are placed at the head of the program. If the global variable is not used, this area can be omitted in the program.

(2) Program

One program starts with the PROGRAM statement of the robot language and ends with the END statement. The program described at the beginning of the file becomes the main program. In the automatic operation mode, the program is executed from the beginning.

Each statement of the robot language is described on each line.

In one program, two or more programs can be described.

For details of the robot language, see the manual, "Robot Language".

(3) Positional Data

The positional data are described in the data block, following the program, at the end of the file.

The data block starts with a DATA statement and ends with an END statement.

The data block stores coordinate data and load data in addition to the positional data.

Each data is designated on each line.

The format of each data is as follows:

[1] Positional data

POINT

<Position name>=<X>,<Y>,<Z>,<C>,<T>/<config>

<Position name> : Name of positional data

<X> ┐:

<Y> : Coordinate values of X, Y, and Z (unit: mm)

<**Z>** [→] :

<C> : Rotating angle of tool end (unit: deg)

<T> : Data of axis 5

<Physical orientation> : Configuration of arm of horizontal articulated type robot

Omitted ... Not defined

LEFTY ... Left handed system RIGHTY ... Right handed system

When the values of X, Y, Z, C and T are omitted, they are treated as 0.

[2] Coordinate data

TRANS

<Coordinate name>=<X>,<Y>,<Z>,<C>

<Coordinate name> : Name of coordinate data

<X> :

Coordinate values in directions of

axes X, Y, and Z (unit: mm)
:

<C> : Rotating angle around axis Z (unit: deg)

When the values of X, Y, Z, and C are omitted, they are treated as 0.

[3] Load data

PLAYLOAD

<Load name>=<mass>, <center-of-gravity offset>

<Load name> : Name of load data

<Mass> : Weight of load applied at the end of the robot hand

(unit: kg)

<Center-of-gravity offset> : Offset of the center of gravity of load applied to the

end of the robot hand from the center of the tool axis

(unit: mm)

When the values of the mass and center-of-gravity offset are ignored, they are treated as 0.

[4] Designation of work coordinate system

The positional data represent the position in the work coordinate system. The positional data are designated by the work coordinate system.

When the work coordinate system is designated, the positional data described in the next line are treated as the position in the work coordinate system. When the work coordinate system is not designated, it is assumed that the work coordinate system accords with the world coordinate system.

The work coordinate system is described in the following format.

WORK < Coordinate name>


<Coordinate name> : Name of coordinate data used as work coordinate system

(3) Example of User File

Examples of the user file is as follows:

A block end code (0AH) is attached to the end of each line (or block).

File name: TEST



DATA POINT A1=400,0,200,0,0/RIGHTY POINT A2-400,200,200,0,0/RIGHTY POINT A3=400,200,50,0,0/RIGHTY POINT A4=400,-200,200,0,0/LEFTY POINT A5=400,-200,50,0,0/LEFTY TRANS W1=400,200,50,90 TRANS W2=400,-200,50,0 PAYLOAD HAND1=3,100 PAYLOAD HAND2=5,0 WORK W1 POINT A11=50,0,60,-45,0/RIGHTY WORK W1 POINT A12=0,50,70,0,0/RIGHTY WORK W1 POINT A13=-50,0,60,45,0/RIGHTY WORK W2 POINT A21=-80,0,60,30,0/LEFTY WORK W2 POINT A22=0,30,70,0,0/LEFTY WORK W2 POINT A23=-80,0,60,-30,0/LEFTY END

Position in world coordinate system

Coordinate data W1 Coordinate data W2 Load data HAND1 Load data HAND2

Position of work coordinate system = W1

Position of work coordinate system = W2

Data block

Section 5

Robot Operation Sequences

Operating procedures for the robot in the External Automatic Mode are basically the same as those in the Internal Automatic Mode.

5.1 Basic Operation

Figure 5.1 presents a flow sequence in which a certain block is selected and executed repeatedly.

5.2 Program Download

Figure 5.2 presents a flow sequence in which a program is downloaded at the completion of each cycle.

5.3 Reinitializing and Starting a Stopped Program

Figure 5.3 presents a flow sequence which reinitializes and starts a program which has been stopped.




Fig. 5.1 Basic operation sequence




Fig. 5.2 Operation sequence including program download




Fig. 5.3 Restart after program interruption

Section 6 Appendix

6.1 ASCII Code

riig	n-order	4 bits \rightarrow	<u> </u>	1		1	1				нех	ade	cim	aı nı	ımb	<u>er —</u>
	0	1	2	3	4	5	6	7	8	9	Α	В	С	D	Е	F
0		D E		0	@	Р	,	р								
1	S H	D 1	!	1	А	Q	а	q								
2	S X	D 2	"	2	В	R	b	r								
3	E X	D 3	#	3	С	S	С	s								
4	E T	D 4	\$	4	D	Т	d	t								
5	E Q	N K	%	5	E	U	е	u								
6	A K	S N	&	6	F	٧	f	v								
7	B L	E B	٤	7	G	W	g	w								
8	B S	C N	(8	Н	Х	h	х								
9	H T	E M)	9	I	Υ	i	у								
Α	L F	S B	*	:	J	Z	j	z								
В	H M	E C	+	;	K	[k	(
С	C L	\rightarrow	,	<	L	¥	I									
D	C R	←	-	=	М]	m)								
Е	S O	↑	-	>	N	٨	n	~								
F	S	+	/	?	0	_	0									

Hexadecimal number

* : Code 00 to 1F correspond to control characters. These characters will either be interpreted as a space (A) or as a code having a specific meaning. The meaning of these codes is shown in the above table.

APPROVED BY: Y. Yamaguchi

CHECKED BY: X. Xata

PREPARED BY: K. Katsumata